



# unIFY Control Panel Installation



QSC, LLC • 1675 MacArthur Boulevard • Costa Mesa, CA 92626  
Ph: 800/854-4079 or 714/957-7100 • Fax: 714/754-6174

© 2020 QSC, LLC all rights reserved. QSC and the QSC logo are registered trademarks of QSC, LLC in the U.S. Patent and Trademark office and other countries. All other trademarks are the property of their respective owners. Patents may apply or be pending.

[www.qsc.com](http://www.qsc.com)

## Installation

**\*Note:** It is recommended that the installation instructions be read prior to attempting installation of the software.

### PC Requirements

- Windows 7, 8, 8.1, or 10 (32- or 64-bit versions)
- Wired Ethernet Network Interface Card

### Installation Method:

The software is installed using a single install file which is available from the registered downloads section of the Attero Tech website.

To install the application, double click of the application EXE file to start the application install. At any point during this installation prior to actually installing the files, the installation may be stopped by clicking on the “Cancel” button.

The application is installed by default into C:\Program Files (x86)\Attero Tech\unIFY Control Panel. This location may be changed by clicking on the “Options” button.

A new default location can be typed into the box or click the “Browse” button to browse for the new location. Click OK to accept any changes. Click “Cancel” to undo any changes

To activate the “Install” button, read the license agreement and if you agree, check the “I accept...” option. Finally, click the “Install” button to initiate the installation of the files.

At this point, Windows may pop up a User Access Account window. If it does, click the “Yes” button to allow the installation to continue.



The installer will then begin copying files and display the progress of the installation.



After this process is successfully completed, click "Close".

The installation will create a program group and various shortcuts including one to run the program. All of the icons are located under Start Menu -> All Programs -> Attero Tech -> Unify Control Panel.

**\*Note:** The installer also installs a copy of the previous revision (V1.7.x) too for devices like older versions of the unD4I-L that are not supported in the latest version of unIFY and cannot be field updated to a version that is supported. There is no icon created for this version but the .exe can be run by locating the file in the installation folder and running it from there.